



# Virtuozzo Containers for Windows 6.0

Reference Guide

April 21, 2016

Parallels IP Holdings GmbH  
Vordergasse 59  
8200 Schaffhausen  
Switzerland  
Tel: + 41 52 632 0411  
Fax: + 41 52 672 2010  
[www.virtuozzo.com](http://www.virtuozzo.com)

Copyright © 1999-2016 Parallels IP Holdings GmbH and its affiliates. All rights reserved.

This product is protected by United States and international copyright laws. The product's underlying technology, patents, and trademarks are listed at <http://www.virtuozzo.com>.

Microsoft, Windows, Windows Server, Windows NT, Windows Vista, and MS-DOS are registered trademarks of Microsoft Corporation.

Apple, Mac, the Mac logo, Mac OS, iPad, iPhone, iPod touch, FaceTime HD camera and iSight are trademarks of Apple Inc., registered in the US and other countries.

Linux is a registered trademark of Linus Torvalds.

All other marks and names mentioned herein may be trademarks of their respective owners.

# Contents

<b>Introduction .....</b>	<b>5</b>
About Virtuozzo Containers for Windows 6.0 .....	5
About This Guide .....	6
Organization of This Guide .....	7
Getting Help.....	7
<b>Virtuozzo Containers for Windows Utilities Overview .....</b>	<b>9</b>
<b>General-Purpose Tools .....</b>	<b>11</b>
vzctl.....	11
vzctl create .....	12
vzctl delete, vzctl destroy.....	13
vzctl mount, vzctl umount.....	14
vzctl start, vzctl stop, vzctl restart, and vzctl status.....	14
vzctl set .....	14
vzctl exec, vzctl exec2, and vzctl enter .....	20
vzctl mountext, vzctl umountext .....	20
vzctl partadd, vzctl partdel.....	21
vzctl reinstall .....	21
vzctl shrink .....	22
vzctl defrag.....	22
vzctl addrole, vzctl delrole, vzctl enumrole .....	23
vzlist .....	23
vzlist Output Parameters and Their Modifiers.....	24
vzquota.....	26
vzquota setlimit .....	27
vzquota stat, vzquota show.....	28
<b>Licensing Tools.....</b>	<b>29</b>
vzlicload.....	29
vzlicview.....	30
<b>Migration Tools.....</b>	<b>31</b>
vzmigrate .....	31

vzp2v.....	32
vzmlocal.....	33
<b>Backup and Restoration Tools .....</b>	<b>35</b>
vzabackup .....	35
vzarestore.....	37
vzvssctl.....	39
<b>Template Management Tools .....</b>	<b>40</b>
vzpkgls .....	40
vzpkgdeploy .....	41
vzpkgadd.....	41
vzpkgrm.....	42
<b>Supplementary Tools .....</b>	<b>43</b>
vzkeygen .....	43
vzcache .....	44
vzlscache.....	46
vzuncache .....	46
vznetcfg.....	47
vznetstat.....	49
vzdevctl .....	49
vzcpucfg.....	51
vzquery.....	52
vzwupdatecmd.....	52
Custom Action Scripts .....	53
<b>Glossary.....</b>	<b>54</b>
<b>Index .....</b>	<b>55</b>

## CHAPTER 1

# Introduction

This chapter provides general information about Virtuozzo Containers for Windows commands and this guide.

### In This Chapter


About Virtuozzo Containers for Windows 6.0 .....	5
About This Guide .....	6
Getting Help.....	7

## About Virtuozzo Containers for Windows 6.0

Virtuozzo Containers for Windows 6.0 is a patented OS virtualization solution. It creates isolated partitions, or Containers, on a single physical server and OS instance to utilize hardware, software, data center and management effort with maximum efficiency. The basic Virtuozzo Containers for Windows capabilities are:

- Intelligent Partitioning. Division of the server into as many as hundreds of Containers with full server functionality.
- Complete Isolation. Containers are secure and have complete functional, fault, and performance isolation.
- Dynamic Resource Allocation. The CPU, memory, network, disk and I/O resources can be adjusted without rebooting.
- Mass Management. The suite of tools and templates for automated, multi-Container and multi-server administration.

The diagram below represents a typical Virtuozzo Containers for Windows system structure:



The Virtuozzo Containers for Windows OS virtualization model is streamlined for the best performance, management, and efficiency. At the base resides a standard Windows host operating system. Next is the virtualization layer with a proprietary file system and a kernel service abstraction layer that ensure the isolation and security of resources between different Containers. The virtualization layer makes each Container appear as a standalone server. Finally, the Container itself houses the applications and workload.

The Virtuozzo Containers for Windows OS virtualization solution has the highest efficiency and manageability, making it the best solution for organizations concerned with containing the IT infrastructure and maximizing resource utilization. The complete set of management tools and unique architecture make Virtuozzo Containers for Windows the perfect solution for easily maintaining, monitoring, and managing virtualized server resources for consolidation and business continuity configurations.

## About This Guide

This guide is a complete reference on all Virtuozzo Containers for Windows configuration files and Hardware Node command-line utilities. It familiarizes you with the way to configure Virtuozzo Containers for Windows to meet your requirements and to perform various tasks by using the corresponding Virtuozzo command line utilities.

The primary audience for this guide is anyone who is looking for an explanation of a particular configuration option, does not understand a Virtuozzo file format, needs help for a particular command, or is seeking for a command to perform a certain task.

## Organization of This Guide

This guide is organized as follows:

- **Chapter 1, Introduction**, gives an overview of Virtuozzo Containers for Windows and this guide.
- **Chapter 2, Virtuozzo Containers for Windows Utilities Overview**, lists all utilities supported in the current version of Virtuozzo Containers for Windows.
- **Chapter 3, General Utilities**, describes utilities for performing day-to-day maintenance tasks.
- **Chapter 4, Licensing Utilities**, provides information on utilities for managing Virtuozzo Containers for Windows licenses.
- **Chapter 5, Migration Utilities**, focuses on utilities for migrating Containers between or within Hardware Nodes.
- **Chapter 6, Backup Utilities**, describes utilities for backing up and restoring Container private areas and configuration files.
- **Chapter 7, Template Management Utilities**, focuses on utilities for creating and managing templates.
- **Chapter 8, Miscellaneous Utilities**, concentrates on utilities for performing miscellaneous tasks in the Hardware Node and Container context.

## Getting Help

In addition to this guide, there are a number of other resources available for Virtuozzo Containers for Windows 6.0 which can help you use the product more effectively. These resources include:

- *Getting Started With Virtuozzo Containers for Windows 6.0*. This guide provides basic information on how to install Virtuozzo Containers for Windows 6.0 on your server, create new Containers, and perform main operations on them.
- *Virtuozzo Containers for Windows 6.0 Installation Guide*. This guide provides exhaustive information on the process of installing, configuring, and deploying your Virtuozzo Containers for Windows system. Unlike the *Getting Started With Virtuozzo Containers for Windows 6.0* guide, it contains a more detailed description of all the operations needed to install and set Virtuozzo Containers for Windows 6.0 to work including planning the structure of your Virtuozzo Containers for Windows network, performing the Virtuozzo Containers for Windows unattended installation, etc. Besides, it does not include the description of any Container-related operations.
- *Virtuozzo Containers for Windows 6.0 User's Guide*. This guide provides comprehensive information on Virtuozzo Containers for Windows 6.0 covering the necessary theoretical

conceptions as well as all practical aspects of working with Virtuozzo Containers for Windows. However, it does not deal with the process of installing and configuring your Virtuozzo Containers for Windows system.

- *Virtuozzo Containers for Windows 6.0 Templates Management Guide*. This guide is meant to provide complete information on Virtuozzo Containers for Windows templates, an exclusive Virtuozzo Containers for Windows technology allowing you to efficiently deploy standard Windows applications inside your Containers and to greatly save the Hardware Node resources (physical memory, disk space, etc.).
- *Virtuozzo Automator Online Help*. This help system shows you how to work with Virtuozzo Automator, a tool providing you with the ability to manage Hardware Nodes and their Containers with the help of a standard Web browser on any platform.
- *Virtuozzo Power Panel Online Help*. This help system deals with Virtuozzo Power Panel, a means for administering individual Containers through a common Web browser on any platform.

# Virtuozzo Containers for Windows Utilities Overview

This chapter documents the utilities supported in the current version of Virtuozzo Containers for Windows. For every utility, all available command-line options are described.

The Virtuozzo Containers for Windows command-line utilities can be subdivided into the following categories: general utilities, licensing utilities, Container migration utilities, Container backup utilities, template management utilities, and miscellaneous utilities.

*General utilities* for performing day-to-day maintenance tasks:

Name	Description
<b>vzctl</b>	Container management utility.
<b>vzlist</b>	Displays a list of Containers existing on the Node with additional information.
<b>vzquota</b>	Manages Virtuozzo Containers for Windows disk quotas.

*Licensing utilities* for managing Virtuozzo Containers for Windows licenses:

Name	Description
<b>vzlicview</b>	Shows the Virtuozzo Containers for Windows license status and parameters.
<b>vzlicload</b>	Installs Virtuozzo Containers for Windows licenses.

*Container migration utilities* for migrating Containers between or within Hardware Nodes:

Name	Description
<b>vzmigrate</b>	Migrates Containers to another Hardware Node.
<b>vzmlocal</b>	Migrates Containers within the same Hardware Node.
<b>vzp2v</b>	Migrates physical servers to Containers.

*Container backup utilities* for backing up and restoring Container private areas and configuration files:

Name	Description
<b>vzabackup</b>	Backs up Containers.
<b>vzarestore</b>	Restores Containers.
<b>vzvssctl</b>	Suspends/resumes Container activity during backups.

*Template management utilities* allow you to create new templates, install them on Hardware Nodes, and other operations:

Name	Description
<b>vzpkgls</b>	Displays templates installed on the Hardware Node and/or applied to Containers.
<b>vzpkgdeploy</b>	Install/removes templates on/from the Hardware Node.
<b>vzpkgadd</b>	Adds application templates to Containers.
<b>vzpkgrm</b>	Removes templates from Containers.

*Miscellaneous utilities* perform different tasks in the Hardware Node and Container context:

Name	Description
<b>vzkeygen</b>	Show the Hardware Node ID.
<b>vzcache</b>	Caches common files across Containers.
<b>vzlscache</b>	List folders created by <code>vzcache</code> .
<b>vzuncache</b>	Detaches Containers from their caches, copies cached files back to the Container private area.
<b>vznetcfg</b>	Manages virtual networks and network classes on the Hardware Node.
<b>vznetstat</b>	Displays traffic usage statistics for Containers.
<b>vzdevctl</b>	Forwards hardware devices (SCSI, iSCSI, USB flash drives, etc.) from the Hardware Node to Containers.
<b>vzcpucfg</b>	Manages CPU pools on the Hardware Node.
<b>vzquery</b>	Determines Container IDs using process and session IDs.
<b>vzwinupdatecmd</b>	Manages Windows Server updates inside Containers.

## CHAPTER 3

# General-Purpose Tools

This chapter describes tools for performing day-to-day maintenance tasks.

### In This Chapter

vzctl .....	11
vzlist .....	23
vzquota.....	26

## vzctl

The primary tool for Container management. To use it, you have to log in to the Hardware Node as the administrator.

### Syntax

```
vzctl [--quiet|--verbose] command <CT_ID>  
vzctl --version  
vzctl --help
```

### Commands

Name	Description
<b>create</b>	Creates a Container.
<b>delete</b>	Removes a Container.
<b>destroy</b>	Removes a Container.
<b>mount</b>	Mounts the Container private area.
<b>umount</b>	Unmounts the Container private area.
<b>start</b>	Starts a Container.
<b>stop</b>	Stops a Container.
<b>restart</b>	Restarts a Container.
<b>status</b>	Displays the Container status.
<b>set</b>	Sets Container parameters.
<b>enter</b>	Provides a way for the Hardware Node administrator to “enter” a Container without knowing the Container administrator password.

<b>exec, exec2</b>	Run arbitrary commands inside a Container without logging in to the Container. The difference between the command is their returned status.
<b>mountext</b>	Mounts folders and drives of the Hardware Node to Containers.
<b>umountext</b>	Unmounts external folders and drives of the Hardware Node from Containers.
<b>partadd</b>	Creates a new Container drive by mounting it to a loopback file on the Hardware Node.
<b>partdel</b>	Unmounts the Container drive mounted by means of the <code>vzctl partadd</code> command.
<b>reinstall</b>	Restores the original state of the Container system and application files.
<b>shrink</b>	Shrinks compact virtual disk drives inside Containers.
<b>defrag</b>	Defragments Container virtual disks
<b>addrole</b>	Adds a new server role to the Container.
<b>delrole</b>	Removes a server role from the Container.
<b>enumroles</b>	Lists the server roles installed or ready to be installed inside Containers.

### Verbosity Options

Name	Description
<b>--quiet</b>	Disables logging to the display and to the log file.
<b>--verbose</b>	Sets the log level to the maximum possible value.

### Miscellaneous Options

Name	Description
<b>--version</b>	Displays the Virtuozzo Containers for Windows version installed on the Hardware Node.
<b>--help</b>	Displays the <code>vzctl</code> usage information.

## vzctl create

Creates new Containers.

### Syntax

```
vzctl create <CT_ID> --pkgset <name> [options]
```

A Container ID is required for this command and shall be unique within a Hardware Node. Container IDs from 1 to 100 are reserved for internal Virtuozzo Containers for Windows needs. Do not use IDs from 1 to 100 for your Containers.

### Options

Name	Description
<b>--pkgset</b> <name>	Mandatory. Denotes the OS template to base the Container on.

<b>--ipadd</b> <IP_address>	Optional. Adds the specified IP address to the list of IP addresses the Container can use and brings up the network interface with this address inside the Container.
<b>--hostname</b> <hostname>	Optional. The hostname to assign to the Container.
<b>--config</b> <filename>	Optional. Applies the resource parameters from the specified configuration file to the Container. Configuration files are located in the <code>X:\Program Files\Parallels\Containers\Configs</code> folder on the Hardware Node and have the form <code>ve-&lt;name&gt;.conf-sample</code> .
<b>--name</b> <name>	An arbitrary name to assign to the Container. This name can be used, along with the Container ID, to refer to the Container while performing Container-related operations.
<b>--private</b> <path>	Optional. Specifies the location of the Container private area. The Container private area can be placed anywhere on your hard disk. While choosing a path for this folder, keep in mind the following: <ul style="list-style-type: none"> <li>• This folder cannot be a mount point, i.e. you cannot mount external disk partitions to this folder.</li> <li>• This folder cannot be a network share, i.e. it cannot be located on a server network drive.</li> <li>• The hard disk partition where this folder will be located must have no less than 10 Gb of free disk space.</li> </ul>
<b>--diskspace</b> <size>	The total size of disk space to allocate to the Container, in 1 Kb blocks.
<b>--disktype</b> <plain   compact>	Optional. The type of the Container virtual disk drive. It can be one of the following: <ul style="list-style-type: none"> <li>• <code>plain</code>: in this case, the size of a virtual hard disk is fixed, i.e. all disk space is allocated during the virtual disk creation.</li> <li>• <code>compact</code> (default): in this case you set only the maximal size of a virtual hard disk. A Container hard disk grows in size each time new data is written to the hard disk and can increase up to the maximum size specified during the hard disk creation.</li> </ul>

## vzctl delete, vzctl destroy

Deletes a Container from the Hardware Node.

### Syntax

```
vzctl delete <CT_ID>
vzctl destroy <CT_ID>
```

When executed, `vzctl delete` or `vzctl destroy` physically removes all the files located in the Container private area with the default path of `C:\vz\private\CT_ID`. These commands do not take any additional arguments and require the Container to be stopped and its private area to be unmounted.

## vzctl mount, vzctl umount

Mounts or unmounts Container's private area to Container's root folder ( $X:\backslash\text{vz}\backslash\text{root}\backslash\langle CT\_ID\rangle$ ) without starting it and Container's registry branch to  $HKEY\_LOCAL\_MACHINE\backslash\langle CT\_ID\rangle$  in the Node's registry.

### Syntax

```
vzctl mount <CT_ID>  
vzctl umount <CT_ID>
```

**Note:** Normally, you do not have to use these commands, because `vzctl start` and `vzctl stop` mount and unmount Container's private area and registry automatically.

## vzctl start, vzctl stop, vzctl restart, and vzctl status

Starts, stops, restarts a Container, or queries its status.

### Syntax

```
vzctl start <CT_ID>  
vzctl stop <CT_ID>  
vzctl restart <CT_ID>  
vzctl status <CT_ID>
```

**Note:** Certain commands can only be performed after using `vzctl stop` (for example, `vzctl delete`).

## vzctl set

Sets Container parameters.

### Syntax

```
vzctl set <CT_ID> [options] [--save]
```

The optional `--save` switch instructs `vzctl` to save changes to the Container configuration file. Most of the Container settings can be changed dynamically without Container reboot.

### General Options

Name	Description
<code>--onboot &lt;yes   no&gt;</code>	This setting requires the <code>--save</code> switch. If you set it to "yes", Virtuozzo Containers for Windows will automatically start the Container on the next system start-up.

<p><b>--userpasswd</b> &lt;user:password&gt;</p>	<p>This setting is used to set a new password for the specified user inside the Container (this user must already exist).</p> <p>Omitting the user name (e.g., :xxxxxxxx) will set the password for the built-in Administrator account inside the Container, even though it was renamed.</p>
<p><b>--offline_management</b> &lt;yes no&gt;</p>	<p>This setting enables/disables the direct managing of the Container through a common Internet browser by means of Virtuozzo Power Panel. To enable/disable the offline management feature for the Hardware Node and, consequently, for all Containers, set this parameter for Container 0.</p>
<p><b>--showctid</b> &lt;yes no&gt;</p>	<p>This setting defines the appearance of the Container ID string in the top right corner of the Container desktop:</p> <ul style="list-style-type: none"> <li>• If set to <code>yes</code>, the ID string is displayed in the top right corner of the Container desktop helping you identify the ID of the Container you are currently logged in to.</li> <li>• If set to <code>no</code>, the ID string is not shown on the Container desktop.</li> </ul> <p>By default, this option is set to <code>yes</code>. Keep in mind that you must log off from the Container and log in to it anew for the changes to take effect.</p> <p>To disable the appearance of the ID string for all Containers that you will create on the Hardware Node, specify 0 as the Container ID when executing the <code>vzctl set</code> command.</p>
<p><b>--showhostname</b> &lt;yes no&gt;</p>	<p>This setting defines the appearance of the Container hostname string in the top right corner of the Container desktop:</p> <ul style="list-style-type: none"> <li>• If set to <code>yes</code>, the hostname string is displayed in the top right corner of the Container desktop helping you identify the hostname of the Container you are currently logged in to.</li> <li>• If set to <code>no</code>, the string is not shown on the Container desktop.</li> </ul> <p>By default, this option is set to <code>no</code>. Keep in mind that you must log off from the Container and log in to it anew for the changes to take effect.</p> <p>To disable the appearance of the hostname string for all Containers that you will create on the Hardware Node, specify 0 as the Container ID when executing the <code>vzctl set</code> command.</p>
<p><b>--name</b> &lt;name&gt;</p>	<p>An arbitrary name to assign to the Container. This name can then be used, along with the Container ID, to refer to the Container while performing Container-related operations.</p>
<p><b>--description</b> &lt;desc&gt;</p>	<p>Sets the Container description. You are allowed to use only symbols in the 'A -z' and '0-9' ranges in your descriptions.</p>
<p><b>--bootorder</b> &lt;number&gt;</p>	<p>Sets the start-up priority for Containers, starting from 1. The lower number is assigned to the Container, the higher priority it has. Specifying 0 after <code>--bootorder</code> restores the default start order of the Container (defined by its ID).</p>
<p><b>--regowner</b> &lt;name&gt;</p>	<p>Sets the registered owner name for the Container. By default, this name is set to <code>User</code>.</p>

<code>--reorganization &lt;name&gt;</code>	Sets the registered organization name for the Container. By default, this name is set to <code>Organization</code> .
--	--

## Resource Management Options

These options allow you to control resources a Container can consume.

Name	Description
<code>-p, --numproc &lt;number&gt;</code>	The number of processes allowed to simultaneously run inside the Container. Upon hitting this limit, the Container will not be able to start a new process.
<code>-t, --numsessions &lt;number&gt;</code>	The maximum number of concurrent terminal sessions to a Container.  <b>Note:</b> Windows Server 2008 R2 SP1 and Windows Server 2012 maintain an extra terminal session to each Container. To provide for this, increase the option value by 1.
<code>--cpuunits &lt;units&gt;</code>	CPU power. This is a positive integer number that defines how much CPU time one Container will receive in comparison with the other Containers on the Hardware Node in case all the CPUs of the Node are fully used.
<code>--cpuguarantee &lt;percent&gt;</code>	CPU guarantee. This is a positive integer number that determines the minimal guaranteed share of the CPU time, in percent, the Container is guaranteed to receive.
<code>--cpulimit &lt;percent&gt;[ m ]</code>	CPU limit, in per cent or megahertz (MHz), the Container is not allowed to exceed. This parameter is not set for newly created Containers; so they can consume all free CPU power of the server.  By default, the limit is set in percent. To set the limit in MHz, specify <code>m</code> after the value.  When setting this parameter in per cent, keep in mind that one CPU core makes up 100%. So if the server has 4 CPU cores, the total CPU power will equal 400%.
<code>--numa &lt;yes   no&gt;</code>	Enables/disables the Non-Uniform Memory Access (NUMA) support inside the Container.
<code>--diskspace &lt;number&gt;</code>	The total size of disk space that can be consumed by the Container, in 1 KB blocks. You can additionally use the <code>--drive</code> option to specify for which Container drive the disk space is to be set. If the <code>--drive</code> option is omitted, the disk space limit is set for the <code>C:\</code> drive.
<code>--drive &lt;name&gt;</code>	The name of the drive inside the Container for which the disk space limit is to be set. This option should be used in conjunction with the <code>--diskspace</code> option.
<code>--vprvmem &lt;number&gt;</code>	The size of private or potentially private memory that can be allocated to all applications inside the Container, in megabytes. Shared or potentially shared memory (e.g., memory mapped files) is not included in this resource parameter.

<code>--disktype &lt;plain   compact&gt;</code>	The type of the Container virtual disk drive. You can set the disk type to one of the following: <ul style="list-style-type: none"> <li><code>plain</code>: in this case, the size of a virtual hard disk is fixed, i.e. all disk space is allocated during the virtual disk creation.</li> <li><code>compact</code> (default): in this case, you set only the maximal size of a virtual hard disk. A Container hard disk grows in size each time new data is written to the disk and can increase up to the maximum size specified during the disk creation.</li> </ul>
<code>--pagedpoollimit &lt;number&gt;</code>	The amount of paged-pool memory, in megabytes, that can be allocated to the Container.
<code>--nonpagedpoollimit &lt;number&gt;</code>	The amount of non-paged-pool memory, in megabytes, that can be allocated to the Container.
<code>--cpus &lt;number&gt;</code>	If the Hardware Node has more than one CPU installed, sets the number of CPUs to be available to the Container. The changes made to the Container will take effect on the next Container start.
<code>--rate &lt;class:Kbits&gt;</code>	If traffic shaping is turned on, this parameter specifies the bandwidth limit for the Container. The format is <code>class:Kbits</code> where <code>class</code> is the network class (group of IP addresses) and <code>Kbits</code> is the traffic bandwidth.

## Network-related Options

These options allow you to manage Container's hostname, IP address(es), DNS server address(es), etc.

**Note:** Most of the network options listed below can be used to configure both the default and additional network adapters inside a Container. In the latter case, you need to additionally specify the `--netif` option when running the `vzctl set` command.

Name	Description
<code>--hostname &lt;name&gt;</code>	Sets the hostname for the Container.
<code>--ipadd &lt;addr&gt;</code>	Adds the IP address to the list of IP addresses the Container can use and brings up the network interface with this address inside the Container. You can set several IP addresses and separate them by spaces.
<code>--ipadd &lt;addr/netmask&gt;</code>	Along with adding the IP address to the Container, sets its subnet mask.
<code>--ipdel &lt;addr   all&gt;</code>	Removes the specified IP address from the Container. Specifying <code>all</code> after the option, removes all IP addresses assigned to the Container.
<code>--nameserver &lt;addr&gt;</code>	Sets the DNS server for the Container. More than one server can be specified in the space-separated format.
<code>--searchdomain &lt;domain&gt;</code>	Sets the DNS search domain for the Container. You can specify several domains and separate them by spaces.

<code>--psched &lt;on   off&gt;</code>	<p>Enables/disables the Quality of Service packet scheduler inside the Container. By default, the scheduler is disabled.</p> <div style="border: 1px solid gray; padding: 5px; margin-top: 10px;"> <p><b>Note:</b> If you have enabled the QoS packet scheduler for a running Container, restart the Container for the changes to take effect.</p> </div>
<code>--nettype &lt;bridged   routed&gt;</code>	<p>Sets the operating mode (either bridged or host-routed) for the Container virtual network adapter. By default, this option is set to <code>routed</code>.</p>
<code>--network &lt;network_ID&gt;</code>	<p>Connects the Container virtual network adapter to the specified Virtual Network.</p>
<code>--mac &lt;mac&gt;</code>	<p>The MAC address to be assigned to the Container virtual network adapter.</p>
<code>--gateway &lt;addr&gt;</code>	<p>Specifies the IP address of the device to be used for routing the traffic from the Container virtual network adapter to external networks.</p>
<code>--winsserver &lt;addr&gt;</code>	<p>The IP address of the WINS server to be used by the Container virtual network adapter.</p>
<code>--vpn &lt;on   off&gt;</code>	<p>Enables/disables the Virtual Private Network (VPN) support by the Container virtual network adapter. By default, the VPN support is disabled.</p>
<code>--openvpn &lt;on   off&gt;</code>	<p>Enables/disables OpenVPN support in the Container. All major releases of OpenVPN starting from version 2.3.0 are supported.</p>
<code>--ciscovpn &lt;on   off&gt;</code>	<p>Enables/disables Cisco VPN Client support in the Container. Cisco VPN Client version 5.0.07 is supported.</p>
<code>--msclient &lt;yes   no&gt;</code>	<p>Enables/disables the Client for Microsoft Networks support.</p>
<code>--msserver &lt;yes   no&gt;</code>	<p>Enables/disables the File and Printer Sharing for Microsoft Networks support.</p>
<code>--msloopback &lt;on   off&gt;</code>	<p>Enables/disables the Microsoft Loopback adapter.</p>
<code>--nat &lt;on   off&gt;</code>	<p>Enables/disables the Network Address Translation (NAT) functionality for the Container virtual network adapter. By default, NAT is disabled for any newly created Container network adapters.</p>
<code>--cluster_ip &lt;addr&gt;</code>	<p>Sets the virtual (Network Load Balancing cluster) IP address for the Container virtual network adapter. Can be set in one of these forms:</p> <ul style="list-style-type: none"> <li>• <code>IP_address</code></li> <li>• <code>IP_address:subnet_mask</code></li> <li>• <code>IP_address/subnet_mask</code></li> </ul>
<code>--nlb &lt;yes   no&gt;</code>	<p>Enables/disables the support for the Network Load Balancing (NLB) feature inside the Container. By default, the NLB support is disabled.</p>
<code>--nlb_mode &lt;multicast   unicast&gt;</code>	<p>Sets the operating mode of Network Load Balancing inside the Container. By default, the mode is set to <code>multicast</code>.</p>

<b>--tsmode</b> <admin   app_device   app_user>	<p>Sets the Terminal Services mode for the Container:</p> <ul style="list-style-type: none"> <li>• If set to <code>admin</code>, enables the Remote Desktop for Administration mode for the Container.</li> <li>• If set to <code>app_device</code> (or <code>app</code>), enables the device-based licensing scheme of the Terminal Server mode for the Container.</li> <li>• If set to <code>app_user</code>, enables the user-based licensing scheme of the Terminal Server mode for the Container.</li> </ul> <p>By default, all newly created Containers is set to work in the Remote Desktop for Administration mode during its creation. Container restart is needed for the new setting to come into effect.</p>
<b>--tslicservers</b> <name>	<p>The NETBIOS name or the IP address of the Terminal Server License (TSL) server to be used by the Container. You can specify several TSL servers and separate them by spaces.</p>
<b>--port_mapping</b> <tcp   udp>:<ext_port>-<int_port> [...]	<p>Sets port mapping.</p>
<b>--promiscuous</b> <yes   no>	<p>Enables/disables the promiscuous mode for the Container network adapter.</p>
<b>--broadcasts</b> <on   off>	<p>Enables/disables the Container network adapter to receive network broadcasts. This option is valid only for Containers operating in the host-routed mode.</p>
<b>--failover_cluster</b> <yes   no>	<p>Enables/disables the support for the Microsoft clustering software inside the Container.</p> <p>To enable/disable the possibility of using the clustering software for all Containers on the Hardware Node at once, specify 0 as &lt;CT_ID&gt;.</p>
<b>--scsi</b> <yes   no>	<p>Enables/disables SCSI-aware drivers to load inside the Container.</p> <p>To enable/disable the loading of SCSI-aware drivers for all Containers on the Hardware Node at once, specify 0 as &lt;CT_ID&gt;.</p>
<b>--dhcp</b> <on   off>	<p>When set to <code>on</code>, enables the Container network adapter to get IPv4 configuration settings via the DHCP protocol. By default, this option is set to <code>off</code>.</p>
<b>--dhcp_ipv6</b> <on   off>	<p>When set to <code>on</code>, enables the Container network adapter to get IPv6 configuration settings via the DHCP protocol. By default, this option is set to <code>off</code>.</p>
<b>--dns_suffix</b> <suffix>	<p>Sets the Domain Name System (DNS) suffix for the Container.</p>
<b>--iplock</b> <on   off>	<p>Enables/disables the possibility of configuring IP address settings and DHCP support from inside the Container.</p>
<b>--netcfglock</b> <on   off>	<p>Enables/disables the possibility of configuring WINS server and DNS suffix settings from inside the Container.</p>

<code>--netif_add &lt;name&gt;</code>	Creates a new virtual network adapter for the Container with the name specified.
<code>--netif_del &lt;name/GUID&gt;</code>	Removes the virtual network adapter with the specified name or GUID (globally unique identifier) from the Container.
<code>--netif &lt;name&gt;</code>	Specifies the name of the Container virtual network adapter whose settings you want to configure. Omit this option if you have only one network adapter inside a Container.
<code>--allow_ip_spoof &lt;yes   no&gt;</code>	Enables or disables IP spoofing for the specified Container. Set to <code>yes</code> by default.
<code>--allow_mac_spoof &lt;yes   no&gt;</code>	Enables or disables MAC spoofing for the specified Container. Set to <code>no</code> by default.
<code>--jumboframe &lt;size&gt;</code>	Specifies jumbo frame size in bytes for the Container network interface. Set to 0 to disable jumbo frames.

## vzctl exec, vzctl exec2, and vzctl enter

Runs arbitrary commands inside a Container.

### Syntax

```
vzctl <exec|exec2> <CT_ID> <command>
vzctl enter <CT_ID>
```

where *command* is a string to be executed in the Container.

The difference between `exec` and `exec2` is the exit code. `vzctl exec` returns 0 in case `vzctl` has been able to launch the command and does not take into account the exit code of the command itself. `vzctl exec2` returns the exit code of the command executed in the Container.

`vzctl enter` is similar to `vzctl exec`. The difference between the two is that `vzctl enter` makes the command line believe that it is connected to a terminal. As such, you receive a command line prompt and are able to execute multiple commands as if you were logged in to the Container.

## vzctl mountext, vzctl umountext

Mounts a drive on the Hardware Node to a drive or folder inside a Container.

### Syntax

```
vzctl mountext <CT_ID> --srcdir <path> --dstdir <path>
```

### Options

Name	Description
<code>&lt;CT_ID&gt;</code>	The ID of the Container where to mount the drive/folder.

<code>--srcdir &lt;path&gt;</code>	The full path to the drive/folder inside the Container where to mount the drive. The drive from the Node can be mounted to any drive/folder inside the Container. If the specified drive/folder does not exist, it is automatically created.
<code>--dstdir &lt;path&gt;</code>	The full path to the drive on the Node.

## vzctl partadd, vzctl partdel

The `vzctl partadd` command creates a new drive inside a Container by mounting it to a loopback file on the Hardware Node. The `vzctl partdel` command unmounts the Container drive mounted with `vzctl partadd` from a file on the Hardware Node.

### Syntax

```
vzctl partadd <CT_ID> --drive <CT_drive> [--size <drive_size>] [--file <filename>]
vzctl partdel <CT_ID> --drive <CT_drive> [--delete]
```

### Options

Name	Description
<code>--drive &lt;CT_drive&gt;</code>	Assigned drive name in one of these formats: <code>X</code> , <code>X:</code> , <code>X:\</code> .
<code>--size &lt;drive_size&gt;</code>	Drive size, in kilobytes.
<code>--file &lt;filename&gt;</code>	File to create on the Node. Upon the command completion, it will have the <code>.efd</code> extension and will be located in the <code>X:\vz\private\CT_ID</code> folder on the Node. If you omit this option, the disk will be assigned a name in the <code>1pbkXXXX.efd</code> format.
<code>--delete</code>	Removes the file the Container drive has been mounted to from the <code>X:\vz\private\CT_ID</code> folder on the Node. If this option is omitted, the file remains.

## vzctl reinstall

Restores the original state of the Container system and application files. The Container is restored to the state it has been in at the time of creation and/or when other applications were added to the Container afterwards.

### Syntax

```
vzctl reinstall <CT_ID> [options]
```

### Options

Name	Description
<code>--resetpwdb</code>	Removes the Administrator credentials from the users' database and creates a clean database as for any new installation.  <b>Note:</b> During Container reinstallation, the username is always reset to

	Administrator whether this option is used or not.
<b>--skipbackup</b>	The contents of the old private area are not saved in the <code>reinstall</code> folder.
<b>--skipapps</b>	Skips reinstalling the application templates inside the Container.

When executed, the `vzctl reinstall` command creates a new private area for the Container and rewrites the Container from scratch using its configuration file (thus retaining the Container IP address, hostname, resource control parameters, and all the other settings). The contents of the Container old private area are then copied to the `C:\reinstall` folder in the new private area, to retain the user files.

## vzctl shrink

Removes unused space from the specified virtual disk, reducing its footprint on the Hardware Node.

```
vzctl shrink <CT_ID> --drive <CT_drive>
```

### Options

Name	Description
<CT_ID>	Container ID.
<b>--drive</b> <CT_drive>	Drive name in one of these formats: <code>X</code> , <code>X:</code> , <code>X:\</code> .

When using this command, keep in mind the following:

- You can shrink virtual disks inside both running and stopped Containers.
- Shrinking a Container virtual disk does not reduce the maximum capacity of the virtual disk itself.
- You cannot shrink plain virtual disks.

## vzctl defrag

Checks virtual disk fragmentation and defragments it if necessary.

### Syntax

```
vzctl defrag <CT_ID> --drive <CT_drive> [--force] [--analysis]
```

### Options

Name	Description
<CT_ID>	Container ID.
<b>--drive</b> <drive>	The drive to defragment/analyze. Can be specified in one of the following formats: <code>X</code> , <code>X:</code> , <code>X:\</code> .

<b>--force</b>	Force defragmentation. You can use this option if you do not have enough free space on the virtual disk. Keep in mind, however, that forcing defragmentation when there is insufficient disk space may result in partial defragmentation.
<b>--analysis</b>	Analyze the virtual disk without defragmenting it.

## vzctl addrole, vzctl delrole, vzctl enumrole

Adds, removes, or lists server roles, role services, and features inside Containers.

### Syntax

```
vzctl addrole <CT_ID> --role <role_name> [...] [--restart]
vzctl delrole <CT_ID> --role <role_name> [...] [--restart]
vzctl enumroles <CT_ID>
```

### Options

Name	Description
<CT_ID>	Container ID.
<b>--role</b> <role_name> [...]	Role(s) to install or remove. To specify multiple roles, separate them by white spaces.
<b>--restart</b>	Restart the Container once installation or removal is complete.

## vzlist

Lists Containers existing on the Hardware Node and displays additional information about them.

### Syntax

```
vzlist [--all] [--stopped] [--name [CT_ID]] [-o <specifier> [...]] [--no-header]
[CT_ID [...]] [--sort [-]parameter[.specifier]] [--hostname <pattern>]
[--name_filter <pattern>] [--description <desc>] [--quiet] [--verbose]
vzlist --list
vzlist --help
```

### Options

Name	Description
<b>-a, --all</b>	List the Containers existing on the Hardware Node. By default, only running Containers are shown.
<b>-S, --stopped</b>	List only stopped Containers.
<b>-o &lt;specifier&gt;</b>	Display only particular information about the Containers. The parameters that can be used after the <b>-o</b> option are listed in the following subsection. To display a number of parameters in a single

	output, separate them with commas.
<b>-H, --no-header</b>	Do not display column headers.
<b>-L, --list</b>	List all parameters for <code>vzlist</code> .
<b>--help</b>	Display command usage information.
<b>-s, --sort [-]parameter[.specifier]</b>	Sort the Containers in the list by the specified parameter. If "-" is given before the name of the parameter, the sorting order is reversed.
<b>-h, --hostname &lt;pattern&gt;</b>	Display only those Containers whose hostnames correspond to the specified pattern. The following wildcards can be used: *.
<b>-n, --name</b>	If used without any parameters, displays information on all Containers on the Node together with their names. If you indicate the Container ID after this option, displays information on the specified Container only.
<b>--netif, -i &lt;fname&gt;</b>	Displays the IP properties of the network interface <code>fname</code> instead of the default one.
<b>-N, --name_filter &lt;pattern&gt;</b>	Displays only the Container that corresponds to the specified pattern.
<b>-d, --description &lt;desc&gt;</b>	Displays only the Container whose description corresponds to the specified pattern.
<b>--quiet</b>	Disables logging to the display and to the log file.
<b>--verbose</b>	Sets the log level to the maximum possible value.

## vzlist Output Parameters and Their Modifiers

Some parameters that can be used after the `-o` and `-s` switches of the `vzlist` utility can be specified by the "dot+letter" combination following the parameter and denoting one of the following things:

Specifier	Description
<b>.b</b>	The barrier on using the corresponding resource set for the given Container.
<b>.h</b>	The hard limit on using the corresponding resource set for the given Container.

The following parameters are available for using with the utility:

Parameter	Output Column	Description
<b>ctid</b>	<b>CTID</b>	The Container ID.
<b>hostname</b>	<b>HOSTNAME</b>	The Container hostname.
<b>ip</b>	<b>IP_ADDR</b>	The Container IP address.
<b>status</b>	<b>STATUS</b>	Specifies whether the Container is running or stopped.
<b>templates</b>	<b>TEMPLATES</b>	Displays the OS and application templates applied to the Container. If the <code>ctid</code> parameter is not specified, all templates available on the Hardware Node are shown.
<b>rates</b>	<b>RATES</b>	The bandwidth limit set for the Container.
<b>name</b>	<b>NAME</b>	Container name.

description	DESCRIPTION	Container description.
numproc	NPROC	The number of processes allowed to simultaneously run in the Container. Can be used with the <code>.b</code> specifier.
numsessions	SESSIONS	The number of terminal sessions opened to the Container. Can be used with the <code>.b</code> specifier.  <b>Note:</b> Windows Server 2008 R2 SP1 and Windows Server 2012 maintain an extra terminal session to each Container. As a result, this counter remains non-zero even when no user-initiated sessions are open.
diskspace	DQBLOCKS	The total size of disk space consumed by the Container, in 1 Kb blocks. Can be used with the <code>.h</code> specifier defining the hard limit on using disk space.
cpuunits	CPUUNI	Allowed CPU power. This is a positive integer number that defines how much CPU time one Container will receive in comparison with the other Containers on the Hardware Node in case all the CPUs of the Node are fully used.
cpuguarantee	CPUGUARANTEE	CPU guarantee. This is a positive integer number that determines the minimal guaranteed share of the CPU time, in percent, the Container is guaranteed to receive.
cpulimit	CPULIMIT	CPU limit. This is a positive number indicating the CPU time, in percent, the Container is not allowed to exceed.
cpus	CPUS	The number of CPUs available to the Container.
cpupool	CPUPOOL	The CPU pools assigned to the Container.
vprvmem	VPRVMEM	The size of private or potentially private memory that can be allocated to all applications inside the Container, in megabytes. Shared or potentially shared memory (e.g., memory mapped files) is not included in this resource parameter.
pagedpool	PAGEDPOOL	The amount of paged-pool memory, in megabytes, that can be allocated to the Container.
disktype	DISKTYPE	The type of the Container virtual disk drive. It can be one of the following: <ul style="list-style-type: none"> <li><code>plain</code>. The size of a virtual hard disk is fixed and all disk space is allocated during the virtual disk creation.</li> <li><code>compact</code>. Only the maximal size of a virtual hard disk is set. The Container hard disk grows in size each time new data is written to the hard disk and can increase up to the maximum size specified during the hard disk creation.</li> </ul>
bootorder	BOOTORDER	The start-up priority set for the Container. The lower number is assigned to the Container, the higher priority it has.
regowner	REGOWNER	The registered owner name set for the Container.

<b>regorganization</b>	<b>REGORGANIZATION</b>	The registered organization name set for the Container.
<b>flags</b>	<b>FLAGS</b>	Displays miscellaneous options (offline management, the support for using the Microsoft Cluster Server software and loading SCSI-aware drivers, etc.) currently enabled for the Container.
<b>network</b>	<b>NETWORK</b>	The Virtual Network to which the Container virtual adapter is connected.
<b>nettype</b>	<b>NETTYPE</b>	The network operating mode set for the default Container.
<b>gateway</b>	<b>GATEWAY</b>	The IP address of the device used for routing the traffic from the Container to external networks.
<b>nameserver</b>	<b>NAMESERVER</b>	The DNS servers set for the Container.
<b>winsserver</b>	<b>WINSSERVER</b>	The WINS server set for the Container.
<b>clusterip</b>	<b>CLUSTERIP</b>	The virtual (Network Load Balancing cluster) IP address assigned to the Container.
<b>ifname</b>	<b>INTERFACES</b>	The list of virtual network adapters available inside the Container.
<b>tsmode</b>	<b>TSMODE</b>	The Terminal Services mode set for the Container: <ul style="list-style-type: none"> <li><code>admin</code>: the Remote Desktop for Administration mode is currently enabled for the Container.</li> <li><code>app_device</code> (or <code>app</code>): the device-based licensing scheme of the Terminal Server mode is currently enabled for the Container.</li> <li><code>app_user</code>: the user-based licensing scheme of the Terminal Server mode is currently enabled for the Container.</li> </ul>

If a parameter that can be used with a specifier is used without any specifier in the command line; the current usage of the corresponding resource is shown by default.

## vzquota

Configures Container disk quotas, shows Container disk quota statistics.

**Note:** `vzctl` uses `vzquota` to configure Container quotas and you usually do not have to use `vzquota` itself except for checking the current quota statistics.

### Syntax

```
vzquota [--quiet | --verbose] [-b] setlimit <CT_ID> -B <num> [--drive <drive_name>]
vzquota [--quiet | --verbose] [-b] <stat | show> <CT_ID>
vzquota --help
```

## Commands

Name	Description
<b>setlimit</b>	Configure the quota limit for the running quota.
<b>stat</b>	Show quota statistics for the running quota.
<b>show</b>	Show quota usage from the quota file.

## Options

Name	Description
<b>-B, --block-hardlimit &lt;num&gt;</b>	Specifies the disk quota block hard limit, in 1KB blocks.
<b>--drive &lt;drive_name&gt;</b>	Sets the disk drive inside the VPS for which the disk quota limit is to be set.
<b>-t, --type</b>	Shows loopback drive type column.
<b>-s, --size</b>	Shows loopback drive size column.
<b>-b</b>	Enables batch mode.
<b>-v, --verbose</b>	Enables verbose mode. <code>vsquota</code> will print output messages about operation progress. Up to two such options are supported to increase verbosity.
<b>-q, --quiet</b>	Enables quiet mode. Suppress warning and diagnostic messages, display only fatal errors.
<b>--help</b>	Displays command usage information.

## vsquota setlimit

Updates limits for the running Container quota. The command requires at least one limit to be specified.

## Syntax

```
vsquota setlimit <CT_ID> -B <num> [--drive <name>]
```

## Options

Name	Description
<b>-B, --block-hardlimit &lt;num&gt;</b>	Specifies the disk quota block hard limit, in 1 KB blocks. This limit cannot be exceeded by the Container.
<b>--drive &lt;name&gt;</b>	Specifies the disk drive inside the Container for which the disk quota limit will be set.

For its execution, `vsquota setlimit` requires only the ID of the Container and the disk quota limit to be specified. However, you can additionally use the `--drive` option to specify to what Container disk drive the defined quota limit is to be applied.

**Note:** The disk quota limit for all Container disk drives except for the `C:\` drive is set on the fly. To make the disk quota limit changes apply to the `C:\` drive, restart the Container where the drive is located.

### vzquota stat, vzquota show

`vzquota stat` shows quota statistics for the running quota. `vzquota show` shows quota usage from the quota file.

#### Syntax

```
vzquota show <CT_ID>  
vzquota stat <CT_ID>
```

## CHAPTER 4

# Licensing Tools

This chapter provides the information on tools for managing Virtuozzo Containers for Windows licenses.

### In This Chapter

vzlicload.....	29
vzlicview.....	30

## vzlicload

Virtuozzo Containers for Windows license management utility.

### Syntax

```
vzlicload [options]
```

### Options

Name	Description
<b>-p, --product-key</b> < <i>key</i> >	Installs the Virtuozzo Containers for Windows license on the Hardware Node.
<b>-i, --stdin</b>	Makes <code>vzlicload</code> use standard input while installing the Virtuozzo Containers for Windows license on the Hardware Node.
<b>-f, --license-file</b> < <i>path</i> >	The full path to the license file containing the Virtuozzo Containers for Windows license to be installed on the Hardware Node.
<b>-u, --update</b>	Connects to the Virtuozzo Key Authentication (KA) server and updates the license installed on the Hardware Node.
<b>-n, --no-check</b>	Skips license validity check and forcibly connects to the Virtuozzo Key Authentication (KA) server during license update.
<b>-t, --transfer</b>	Transfers the Virtuozzo Containers for Windows license from one Hardware Node (Source Node) to another (Destination Node). You should use this option along with the <code>-p</code> option when running the <code>vzlicload</code> utility on the Destination Node.
<b>-r, --remove</b> < <i>key</i> >	Removes the Virtuozzo Containers for Windows license with the specified serial number from the Hardware Node. You can find out the license serial number using the <code>vzlicview</code> utility (see <b>vzlicview</b> (p. 30)).

<b>-A, --proxy-server</b> <addr/hostname>	The IP address or hostname of the proxy server, if you use any, to connect to the Internet. By default, the Internet Explorer proxy settings are used.
<b>-U, --username</b> <username>	Username for the proxy server.
<b>-P, --password</b> <password>	Password for the username specified with the -U option.
<b>-h, --help</b>	Displays the utility usage and exits.

## vzlicview

Displays license information.

### Syntax

```
vzlicview [options]
```

### Options

Name	Description
<b>-f, --license-file</b> <file>	Displays the license information from the specified Virtuozzo Containers for Windows license file.
<b>-p, --product-key</b> <key>	Displays the license information contained in the specified Virtuozzo Containers for Windows product key.
<b>-i, --stdin</b>	Makes <code>vzlicview</code> use standard input as a license and display its information.
<b>-v, --validate</b>	Displays the total number of Containers which may simultaneously run on the Hardware Node in accordance with the license currently installed on this Node.
<b>-h, --help</b>	Displays command usage information.

### License Statuses

Name	Description
<b>ACTIVE</b>	The license is valid.
<b>INVALID</b>	The license is invalid (for example, because of the Hardware Node ID mismatch) or corrupt.
<b>EXPIRED</b>	The license file matches the Hardware Node ID, but has expired.
<b>GRACED</b>	The license has expired and is currently on the grace period (i.e. it is active till the end of the grace period).

# Migration Tools

This chapter focuses on tools for migrating Containers between Hardware Nodes or within the same Hardware Node.

## In This Chapter

vzmigrate .....	31
vzp2v .....	32
vzmlocal.....	33

## vzmigrate

Moves Containers from a source Node to a destination Node with minimal downtime.

### Syntax

```
vzmigrate [--remove-area <yes|no>] [--nostart] --srv_addr <addr> --srv_user <username>
--srv_pswd <passwd> <source_CTID>[:dest_CTID] [... ]
vzmigrate --help
```

### Options

Name	Description
-r, --remove-area <yes no>	If “yes” is specified, then the private area will be deleted after the corresponding Container is successfully migrated to the destination Node. If “no” is specified, the private area will not be deleted. In this case the Container configuration file will be renamed from <i>CT_ID.conf</i> to <i>CT_ID.conf_migrated</i> . By default, the Container private area is removed from the source Node.
-n, --nostart	Do not start the Container on the destination Node after migration. This option does not have any effect if the Container was not running on the source Node.
-A, --srv_addr <addr>	The IP address or the hostname of the destination Node, i.e. of the Node where the Container is to be migrated.
-U, --srv_user <username>	The username to log in to the destination Node with. Must have administrator rights.
-P, --srv_pswd <passwd>	The password for the username provided with the --srv_user option.
-h, --help	Displays command usage information.
--quiet	Disables logging to the screen and to the log file.

<b>--verbose</b>	Sets the log level to the maximum possible value for this <code>vzmigrate</code> session.
------------------	---

To migrate the Container, execute the `vzmigrate` command on the source Node and pass the corresponding options to it. A different `dest_CTID` parameter is needed in case the source Node (the one where you run `vzmigrate`) and the destination Node have Containers with the same ID. You can specify multiple Containers for migration.

If the Container is running on the source Node, `vzmigrate` copies its private files, registry settings, etc. to the destination Node, stops the Container on the source Node, copies the files changed after the first copying to the destination Node again, and starts the Container on the destination Node (if the `-n` option is not specified).

Since a Container consists of thousands of files, copying all of them to a new Hardware Node may take considerable time. However, `vzmigrate` stops the Container only after all the files have been copied to the new Hardware Node and resynchronizes only those files that have been changed while being copied. This brings down a typical Container downtime to the time required for restarting a Container.

## vzp2v

Migrates a physical server to a Container on the Hardware Node.

### Syntax

```
vzp2v <CT_ID> --src_addr <addr> --src_user <username> --src_passwd <passwd>
[--src_stop] [--ve_start] [--exclude <disk_drive> [...]] [--bridged <vn_ID>]
vzp2v --help
```

### Options

Name	Description
<b>-A, --src_addr</b> <addr>	Mandatory. The IP address or hostname of the physical server you are going to migrate to a Container on your Node.
<b>-U, --src_user</b> <username>	Mandatory. The username to log in to the physical server. The specified user should have the Administrator rights to the server.
<b>-P, --src_passwd</b> <passwd>	Mandatory. The password of the user specified as the value of the <code>-U</code> option.
<b>-s, --src_stop</b>	Optional. Stop the physical server after its successful migration. If this option is omitted, the physical server continues running upon the migration completion.
<b>-v, --ve_start</b>	Optional. Start the Container on the Hardware Node after the physical server has been successfully migrated. If the option is not specified, the Container is not started after the physical server migration.

<b>-x, --exclude</b> <drive>	Optional. The name of the disk drive that you do not wish to move to the Container. The formats that can be used for specifying the drive name are <i>X</i> , <i>X:</i> or <i>X:\</i> where <i>X</i> denotes the name of the drive that is not to be moved to the Container. You can specify several drives to be excluded from the migration process and separate them by spaces. If you omit this option, all disk drives available on the physical server will be migrated to the Container.
<b>-b, --bridged</b> <virt_net_ID>	Optional. If one or more network adapters on the physical server use the DHCP protocol to receive their IP address, you should specify this option to denote the Virtual Network on the Hardware Node where these network adapters are to be connected. If you omit this option, you will need to manually configure the Container network adapter parameters for it to be visible on your network.  Detailed information on Virtual Networks is provided in the <i>Virtuozzo Containers for Windows 6.0 User's Guide</i> .
<b>--help, /?</b>	Displays command usage information.

To migrate a physical server, you should execute the `vzp2v` command on the Hardware Node and pass the corresponding options to it. Before starting the migration process, please make sure that there are no Containers on your Node with the ID you are going to specify as `CT_ID`; otherwise, the migration will fail.

## vzmlocal

Moves/copies Containers within the same Hardware Node. Essentially, this command changes the existing Container ID and private area path to move that Container, or creates a copy of an existing Container with a different ID and private path.

### Syntax

```
vzmlocal [options] <source_CTID>:<dest_CTID>[:<dest_private>] [...]  
vzmlocal --help
```

### Options

Name	Description
<source_CTID>	Source Container ID.
<dest_CTID>	Destination Container ID.
<dest_private>	Destination Container's private path. Overrides the default path ( <i>X:\vz\private\CT_ID</i> ).
<b>-C, --copy</b>	Clones the source Container instead of moving it.
<b>-s, --fast-sid</b>	Speeds up Container cloning by doing a faster SID scan (checks only the registry and files subset).
<b>-d, --destroy-source</b>	Destroys the source Container after cloning.
<b>-n, --disable-network</b>	Disables offline management for the source Container after cloning.
<b>-#, --custom-storage</b>	Clone to custom storage.

<b>-l, --skiplock</b>	Allows you to clone locked Containers.
<b>-S, --sid-change</b> <b>&lt;block   newvpsid   none&gt;</b>	Allows you to specify the SID change method. Default: <code>block</code> . <ul style="list-style-type: none"><li>• <code>block</code>: Changes the SID throughout the new Container's virtual disk.</li><li>• <code>newvpsid</code>: Changes the SID at preset locations inside the new Container.</li><li>• <code>none</code>: Does not change the SID.</li></ul>
<b>--quiet</b>	Disables logging to screen and log file.
<b>--verbose</b>	Sets log level to maximum possible value for this <code>vzmlocal</code> session.
<b>--help</b>	Displays command usage information.

# Backup and Restoration Tools

This chapter describes tools for backing up and restoring Container private areas and configuration files.

## In This Chapter

vzabackup .....	35
vzarestore .....	37
vzssctl .....	39

## vzabackup

Creates backups of Containers or entire Hardware Nodes. The `vzabackup` utility can be run on:

- The Source Node where the Container to be backed up is residing.
- A Backup Node intended for storing Container backups.
- Any other physical server on your network running Virtuozzo Containers for Windows.

The only requirements that should be met to execute `vzabackup` is to have a server with Virtuozzo Containers for Windows and the VA Agent software installed on it and to provide the network connectivity for this server to be able to establish connections to the Source and Backup Nodes, if necessary. The created Container backups are then stored on the Backup Node which can also be presented by any Node with running the Virtuozzo Containers for Windows and VA Agent software.

### Syntax

```
vzabackup [backup_options] <source_node> [...] [CT_options]
```

where `source_node` is the Source Node IP address and credentials as follows: `[user[:passwd]@]<source_node_addr>`. If you omit the credentials, you will be asked to provide them during `vzabackup` execution.

### Backup Options

Name	Description
<code>-F, -I, --TFull</code>	Make a full backup. By default, <code>vzabackup</code> creates a full backup of Containers and Hardware Nodes.

<b>-i, --Tinc</b>	Make an incremental backup or, if no full backups are available, a full backup. If this option is omitted, the full backup is created.
<b>--Tdiff</b>	Make a differential backup or, if no full backups are available, a full backup. If this option is omitted, the full backup is created.
<b>-D &lt;desc&gt;</b>	The description of the backup archive.
<b>-o, --rm-old</b>	Create a new backup and then remove the oldest backup of the specified Node/Container.
<b>--rm-tag &lt;backup_ID&gt;</b>	Create a backup and then remove the backup with the specified ID. You can learn what ID is assigned to what Container backup using the <code>-l</code> and <code>-f</code> options of the <code>vzarestore</code> utility.
<b>-C&lt;n   g   b&gt;</b>	<p>Indicates the level of compression for the resulting Container backup archive. In the current version of Virtuozzo Containers for Windows, you can set this level to one of the following:</p> <ul style="list-style-type: none"> <li><code>n</code>: create the Container backup without any compression. Using this level of compression may speed up the backing up time; however, it may significantly increase the size of the resulting backup file.</li> <li><code>g</code>: compress the resulting backup with the normal level of compression. This is the default level of compression used to back up all Nodes/Containers.</li> <li><code>b</code>: compress the resulting backup with the maximum level of compression. In this case the backup file size is the smallest; however, it may take much time to create the backups.</li> </ul> <p>The optimal data compression level depends on the type of files to be stored in the backup archive. For example, it is advisable to use the 'normal' and 'none' compression types if most of the files to be backed up are already compressed (e.g. the files with the <code>.zip</code> and <code>.rar</code> extensions) or can be compressed with a low degree of efficiency (e.g. all executable files with the <code>.exe</code> extension or image files with the <code>.jpg</code>, <code>.jpeg</code>, and <code>.gif</code> extensions).</p>
<b>-J</b>	If several Source Nodes are specified, back up these Nodes and/or their Containers simultaneously. If the option is omitted, the Nodes are backed up sequentially one after another.
<b>--force</b>	Force the process of backing up the Hardware Node(s)/Container(s). Can be used when backing up several HNs/Containers to continue the backup process even if some errors occur when creating a backup of a certain Node/Container.
<b>--view-folder</b>	Shows current backup storage configuration.
<b>--set-folder-creds &lt;user&gt;[:passwd]</b>	Set backup storage login credentials. Required for Samba shares.
<b>--backup-folder-path &lt;path&gt;</b>	Path to a custom backup storage location.
<b>--backup-folder-login &lt;user&gt;</b>	Username for a custom backup storage on a Samba share.
<b>--backup-folder-passwd &lt;passwd&gt;</b>	Password for a custom backup storage on a Samba share.
<b>--set-folder</b>	Use <code>--backup-folder-*</code> option values to change backup storage configuration.

<b>--storage</b> [ <i>user[:passwd]@</i> ] <i>&lt;addr&gt;</i>	The IP address and the credentials of the Backup Node. If you do not indicate the password to log in to the Backup Node, you will be asked to do so during the <code>vzabackup</code> execution.  If this option is omitted, <code>vzabackup</code> puts the created backup(s) to the backup folder on the Source Node (by default, this folder is <code>X:\vz\Backups</code> ).
<b>-q, --no-progress</b>	Disables logging to the screen during the <code>vzabackup</code> operation.

## Container Options

Name	Description
<b>-e</b> <i>&lt;CT_ID&gt;</i> [ ... ]	The Containers to back up on the Source Node. If this option is omitted, all Containers on the given Node will be backed up. Containers can be specified using both their IDs (e.g. 101 or 102) and their names (e.g. <code>comp1</code> or <code>comp2</code> ).
<b>-x</b> <i>&lt;CT_ID&gt;</i> [ ... ]	The Containers that need not be backed up (Containers to exclude). If this option is omitted, all Containers on the given Source Node will be backed up. Containers can be specified using both their IDs (e.g. 101 or 102) and their names (e.g. <code>comp1</code> or <code>comp2</code> ).
<b>--include-files</b> <i>&lt;list&gt;</i>	Only the specified files and folders will be included in the Container backup.  <b>Note:</b> If you create a Container backup using this option, you will be able to restore only separate files from the resulting Container backup, but not the Container as a whole.
<b>--exclude-files</b> <i>&lt;list&gt;</i>	The path to the files and folders inside the Container to be excluded from the backup.

## vzarestore

Manages Container backups: restores Containers or Container files/folders from the Container backup, lists backups on the Backup Node, removes backups, etc. The `vzarestore` command can be run on any Hardware Node that has VA Agent installed.

### Syntax

```
vzarestore <CT_ID> [restore_options] [backup_node]
vzarestore -e <CT_ID> [ ... ] | -x <CT_ID> [ ... ] [restore_options] [backup_node]
vzarestore -l,--list [list_options] [backup_node]
vzarestore -r,--remove <backup_ID> [ ... ]
vzarestore --browse <backup_ID> [-d <path>] [backup_node]
vzarestore --print-ct-config <backup_ID> [backup_node]
vzarestore --help
```

### Options

Name	Description
<b>-e</b> <i>&lt;CT_ID&gt;</i> [ ... ]	The Containers to be restored on the Destination Node. Any Container can be specified using both its IDs (e.g., 101 or 102) and its names (e.g., <code>comp1</code> or

	comp2).
<b>-x</b> <CT_ID> [ . . . ]	The Containers that need not be restored (the Containers to exclude). Any Container can be specified using both its IDs (e.g., 101 or 102) and its names (e.g., comp1 or comp2).
<b>-b</b> <backup_ID>	The ID assigned to the Container backup. This ID can be used to manage the backup archive (e.g., to delete the Container backup from the Backup Node or restore the files from the Container backup with the specified ID). If this option is omitted, the latest Container backup is used.
<b>--force</b>	Do not stop on errors during the <code>vzarestore</code> execution. Can be used when you are restoring more than one Container. This option allows you to continue the restoring process if some errors occur when restoring a certain Container.
<b>--skip-ct-config</b>	Do not restore the Container configuration file. Can be used only if you are restoring a single Container.  <b>Note:</b> The Container configuration file is not changed when restoring separate Container files.
<b>--files</b> <path>	The full path to the files/folders inside the Container to be restored. This options is incompatible with the <code>-e</code> and <code>-x</code> options.
<b>--backup-folder-path</b> <path>	Path to a custom backup storage location.
<b>--skip-locked</b>	Do not stop on errors even if some of the files to be restored are in the 'locked' state.
<b>-B</b>	Handle the values after the <code>-e</code> and <code>-x</code> options as backup IDs.
<b>--storage</b> [ username[:passwd]@]<addr>	The IP address and the credentials of the Backup Node. If this option is omitted, <code>vzarestore</code> looks for the Container backup on the local Node.
<b>-q, --no-progress</b>	Do not show the progress bar.
<b>-d, --dir</b> <path>	The path to the folder inside the Container backup archive whose contents is to be shown. Used only with the <code>vzarestore --browse &lt;backup_ID&gt;</code> command.
<b>--print-ct-config</b> <backup_ID>	Displays the parameters set in the Container configuration file at the moment of creating the backup with the specified backup ID.
<b>-r, --remove</b> <backup_ID>	Removes the Container backup with the specified backup ID.
<b>--help</b>	Shows command usage information.

### List Options

Name	Description
<b>f, --full</b>	Display detailed information on the backed up Containers.
<b>--latest</b>	Display the latest Container backup.
<b>-e</b> <CT_ID> [ . . . ]	Display the information on the backups for the specified Containers only.
<b>-B</b>	Handle the values after the <code>-e</code> option as backup IDs.

## vzvssctl

Suspends or resumes Container activity (e.g., during backup).

### Syntax

```
vzvssctl <-s|-r> [CT_ID] [...]  
vzvssctl --help
```

### Options

Name	Description
-s	Suspends the Container activity.
-r	Resumes the Container activity.
--help, /?	Displays the utility usage and exits.

# Template Management Tools

This chapter focuses on tools for creating and managing templates.

## In This Chapter

vzpkgls .....	40
vzpkgdeploy.....	41
vzpkgadd.....	41
vzpkgrm.....	42

## vzpkgls

Lists OS and application templates installed on the Hardware Node or applied to a Container. If you specify multiple Container IDs, the utility will list templates applied to these Containers. Without a Container ID as an argument, the utility lists all templates available for Containers on the Hardware Node.

### Syntax

```
vzpkgls [options] [CT_ID] [...]
```

### Options

Name	Description
<b>-d, --deployed</b>	Skips templates which are cached but not installed.
<b>-o, --os</b>	Lists all OS templates installed on the Hardware Node.
<b>-a, --application</b>	Lists all application templates installed on the Hardware Node.
<b>-s, --separate</b>	By default, <code>vzpkgls</code> outputs the template and all its updates on a single line separated by spaces. This option changes the output and prints a separate line for each available version of the template.
<b>-q, --quiet</b>	Disables logging to the display and to the log file.
<b>-h, --help</b>	Displays the usage information and exits.

## vzpkgdeploy

Installs/removes OS and application templates on the Hardware Node.

### Syntax

```
vzpkgdeploy [-q|-v] --install|--uninstall <package> [...]
vzpkgdeploy --help
```

### Options

Name	Description
-i, --install <package> [...]	Installs the template on the Hardware Node.
-u, --uninstall <package> [...]	Removes the template from the Hardware Node.
-h, --help	Displays the usage information and exit.
--quiet	Disables logging to the display and to the log file.
--verbose	Sets the log level to the maximum possible value for this vzpkgdeploy session.

## vzpkgadd

Adds application templates to a running Container.

### Syntax

```
vzpkgadd [options] <CT_ID> <template>[/version] [...]
```

The <version> parameter specifies the template version to use if there are available upgrades. By default, the latest available version is used.

### Options

Name	Description
-h, --help	Display the usage info and exit.
-f, --force	Force template installation.
--quiet	Disables logging to the display and to the log file.
--verbose	Sets the log level to the maximum possible value for this vzpkgadd session.

## vzpkgrm

Uninstalls application templates from a running Container.

### Syntax

```
vzpkgrm [options] <CT_ID> <template>[/version] [...]
```

### Options

Name	Description
-d, --nodeps	Removes templates with unresolved dependencies.
-h, --help	Displays command usage information.
-f, --force	Forces uninstallation of templates.
-q, --quiet	Disables logging to the display and to the log file.
-v, --verbose	Sets the log level to the maximum possible value for this vzpkgrm session.

## CHAPTER 8

# Supplementary Tools

This chapter concentrates on tools for performing various tasks in the Hardware Node and Container context.

### In This Chapter

vzkeygen.....	43
vzcache .....	44
vzlscache.....	46
vzuncache.....	46
vznetcfg .....	47
vznetstat .....	49
vzdevctl.....	49
vzcpucfg .....	51
vzquery .....	52
vzwinupdatecmd.....	52
Custom Action Scripts.....	53

## vzkeygen

Generates a unique Hardware Node ID. To obtain a Virtuozzo Containers for Windows license, send your Node ID together with a license request to the Virtuozzo sales department.

### Syntax

```
vzkeygen [--company-name <name>] [--output-file <filename>]  
vzkeygen --help
```

### Options

Name	Description
-n, --company-name <name>	Your company name
-o, --output-file <filename>	Saves output to a file instead of stdout. If a filename is provided without a path, the output is saved to C:\Documents and Settings\Administrator by default.
-h, --help	Displays command usage information.

## vzcache

There may be situations when one and the same application or application update is installed not as a template, but separately inside several Containers. A good example of this is the Adobe Acrobat Reader application that can be installed inside a number of Containers thus having a vast amount of identical files throughout the Containers. This fact tells dramatically on the Container quotas, which may be avoided by putting all the identical files to the Hardware Node template area and creating links instead of real files inside the affected Containers.

The problem like the one described above is solved by using the `vzcache` utility. The utility scans the specified Containers for common files and caches these files in the Hardware Node template area (in the `X:\vz\templates\__vzcache` folder), replacing the real files inside the Containers with links to the template area (`X:\vz\templates\__vzcache`). In case of a significant number of identical files, using `vzcache` results in a notable disk space gain.

### Syntax

```
vzcache [options] <CT_ID> [...]
```

### Options

Name	Description
<code>-h, --help</code>	Print usage information.
<code>--version</code>	Display the utility version.
<code>-v, --verbose</code>	Verbose mode. Causes <code>vzcache</code> to print debugging messages about its progress. Multiple <code>-v</code> options increase verbosity. The maximal number of allowed options is 2.
<code>-q, --quiet</code>	Quiet mode. Causes all warning and diagnostic messages to be suppressed. Only fatal errors are displayed.
<code>-n, --cache-name &lt;name&gt;</code>	The name of the folder in <code>X:\vz\templates\__vzcache</code> where you want to store the cached files. If you omit this option, <code>vzcache</code> creates a subfolder with a random name.  If used with the <code>-a</code> option, tells <code>vzcache</code> to look for similar files in the specified cache folders.

<b>-a, --append</b> <name>	<p>Look for similar files inside the specified Containers and compare them with the files in the indicated caches and templates. <code>-a</code> requires one of the following options:</p> <ul style="list-style-type: none"> <li>• <code>-n</code>. In this case <code>vzcache</code> compares the files inside the specified Containers with those in the specified caches and replaces them with links, if necessary.</li> <li>• <code>-T</code>. In this case <code>vzcache</code> compares the files inside the specified Containers with those in the specified templates and replaces them with links, if necessary.</li> <li>• <code>-H</code>. In this case <code>vzcache</code> compares the files inside the specified Containers with those in the system partition on the Node and replaces them with links, if necessary.</li> <li>• <code>-A</code>. In this case <code>vzcache</code> compares the files inside the specified Containers with those in all available caches and templates. It does not, however, look for similar files in the system partition on the Node.</li> </ul>
<b>-s, --size-limit</b> <N>	Do not process files smaller than <code>N</code> bytes. By default, only empty files are not processed.
<b>-m, --min-links</b> <M>	Cache files found at least <code>M</code> times. The default value is 2.
<b>-T, --template-name</b> <name>	<p>Look for similar files in the specified OS and application templates. Must be used with the <code>-a</code> option.</p> <p>You can indicate several templates at a time and separate them by commas (e.g., <code>Template1, Template2</code>).</p>
<b>-H, --host</b>	<p>Look for similar files in the system partition on the Hardware Node. Must be used with <code>-a</code> and one of the following options:</p> <ul style="list-style-type: none"> <li>• <code>-A</code></li> <li>• <code>-T OS_Name</code> (where <code>OS_Name</code> denotes the name of the OS template installed on the Node)</li> </ul>
<b>-A, --all</b>	Look for similar files in all caches and templates and in the system partition on the Hardware Node. Must be used with the <code>-a</code> option.
<b>-f, --force</b>	Force the <code>vzcache</code> execution.
<b>-t, --test</b>	Do not perform any caching. Just collect and display the statistics on identical files.

Here are some examples on using the `vzcache` utility:

- To create a cache named `cache1` for Containers 153 and 154 caching only those files which are greater than 1024 bytes by using the `vzcache` utility, you should issue the following command:

```
vzcache -s 1024 -n cache1 153 154
```

- To append Container 155 to the existing `cache1` cache:

```
vzcache -a -n cache1 155
```

## vzlsocache

Displays a list of cache directories created by the `vzcache` utility. Shows either all the cache directories on the given Hardware Node, or those used by the specified Container(s).

### Syntax

```
vzlsocache [options] [CT_ID] [...]
```

### Options

Name	Description
<code>-h, --help</code>	Print utility usage information.
<code>-q, --quiet</code>	Quiet mode. Causes all warning and diagnostic messages to be suppressed. Only fatal errors are displayed.

## vzuncache

Whereas the `vzcache` utility helps effectively gain disk space both in the Hardware Node and within Containers, there may be situations when it is necessary to detach a Container from its cache and copy the cached files back to the Container private area. A typical example of this is migrating a Container to another Hardware Node. The migration is not possible if there are links in the Container private area pointing to the `C:\vz\templates\__vzcache` folder on the Hardware Node.

The `vzuncache` utility is used to copy the regular files from the specified cache directory on the Hardware Node (located in the `C:\vz\templates\__vzcache` folder) back to the private area of the specified Container, replacing the corresponding links or stubs inside the Container with the real files and thus detaching the Container from its cache.

### Syntax

```
vzuncache [options] <CT_ID> [cache_dir] [...]
```

### Options

Name	Description
<code>-h, --help</code>	Print usage information.
<code>--version</code>	Display the utility version.
<code>-q, --quiet</code>	Quiet mode. Causes all warning and diagnostic messages to be suppressed. Only fatal errors are displayed.

<b>-v, --verbose</b>	Verbose mode. Causes <code>vzuncache</code> to print debugging messages about its progress. Multiple <code>-v</code> options increase verbosity.
<b>-a, --all</b>	Detach the specified Container from all the caches. The list of cache directories is not needed if this option is specified.
<b>-t, --test</b>	Do not copy files from the cache. Just collect and display the relevant statistics.
<b>-f, --force</b>	Detach the specified Container from its cache even in case the cache does not exist.

## vznetcfg

The `vznetcfg` utility is used to manage Virtual Networks and network classes on the Hardware Node.

### Syntax

```
vznetcfg <command> [command_options]
vznetcfg --help
```

### Commands

Name	Description
<b>net new</b> <net_ID> <MAC>[:VLAN_ID]	Creates a new Virtual Network with the ID of <code>net_ID</code> and associates it with either: <ul style="list-style-type: none"> <li>a physical adapter on the Hardware Node with the MAC address of <code>MAC</code>, or</li> <li>a Virtual Local Area Network (VLAN) adapter bound to the physical adapter with the MAC address of <code>MAC</code>.</li> </ul>
<b>net change</b> <net_ID> <MAC>[:VLAN_ID]	Associates the specified Virtual Network with the physical or VLAN adapter on the Hardware Node.
<b>net del</b> <net_ID>	Deletes the specified Virtual Network from the Hardware Node.
<b>net list</b>	Lists Virtual Networks existing on the Hardware Node.
<b>class add</b> <class_ID> <IP_range1> [IP_range2 ... IP_rangeN]	Creates a new network class with the ID of <code>class_ID</code> and the specified IP address range(s).  An IP address range should be specified as an IP address, a slash, and a subnet mask or a CIDR suffix. For example, specify <code>10.0.0.0/255.0.0.0</code> or <code>10.0.0.0/8</code> to cover IP addresses from <code>10.0.0.0</code> to <code>10.255.255.255</code> .
<b>class remove</b> <class_ID> [IP_range1 ... IP_rangeN]	Removes the specified IP address range(s) from the specified network class.  If no IP address ranges are specified, removes the entire network class.  An IP address range should be specified as an IP address, a slash, and a subnet mask or a CIDR suffix. For example, specify <code>10.0.0.0/255.0.0.0</code> or <code>10.0.0.0/8</code> to cover IP addresses from

	10.0.0.0 to 10.255.255.255.
<b>class rate</b> <class_ID> <rate>	Sets the maximal network bandwidth, in Kilobits per second, any Container on the Hardware Node is guaranteed to have for outgoing traffic within the specified network class.
<b>class list</b>	Lists network classes existing on the Hardware Node.
<b>shaper</b> <on   off   status>	Enables, disables, or shows the status of the traffic shaper. The traffic shaper can be managed with <code>vzctl</code> and <code>vznetcfg class rate</code> commands.
<b>privnet add</b> <privnet_ID> <IP_range1> [IP_range2 ... IP_rangeN]	Adds a private Virtual Network with one or more IP ranges.  An IP address range should be specified as an IP address, a slash, and a subnet mask or a CIDR suffix. For example, specify <code>10.0.0.0/255.0.0.0</code> or <code>10.0.0.0/8</code> to cover IP addresses from <code>10.0.0.0</code> to <code>10.255.255.255</code> .
<b>privnet remove</b> <privnet_ID> [IP_range1 ... IP_rangeN]	Removes the specified IP range(s) from a private Virtual Network.  If no IP ranges are specified, removes the entire private Virtual Network.  An IP address range should be specified as an IP address, a slash, and a subnet mask or a CIDR suffix. For example, specify <code>10.0.0.0/255.0.0.0</code> or <code>10.0.0.0/8</code> to cover IP addresses from <code>10.0.0.0</code> to <code>10.255.255.255</code> .
<b>privnet list</b>	Lists private Virtual Networks existing on the Hardware Node.
<b>privnet weak</b> <yes   no   show>	Controls private Virtual Network weakness: <ul style="list-style-type: none"> <li>• <code>yes</code> — Allows passing packets from private Virtual Networks to external hosts.</li> <li>• <code>no</code> — Forbids passing packets from private Virtual Networks to external hosts.</li> <li>• <code>show</code> — Shows the current weakness status.</li> </ul>
<b>privnet status</b> [ on   off ]	Enables or disables private Virtual Networks on the Hardware Node.  If no options are specified, shows the private Virtual Network status.
<b>firewall status</b> [ on   off ]	Enables or disables the firewall on the Hardware Node.  If no options are specified, shows the firewall status.
<b>firewall status-all-adapters</b> [ on   off ]	Enables or disables for all adapters rules set with <code>vznetcfg firewall policy</code> . These rules add to any existing policies for specific adapters set with <code>vzctl</code> .  If no options are specified, shows the current firewall status.
<b>firewall policy</b> <default   private   public> [ accept   drop accept   drop ]	Sets a firewall policy of the specified type. The first <code>accept   drop</code> option is for incoming packets, the second is for outgoing packets.  If no <code>accept   drop</code> options are provided, shows the specified firewall policy status.
<b>--help</b>	Displays command usage information.

## vznetstat

Outputs traffic usage statistics for Containers.

### Syntax

```
vznetstat [-v <CT_ID>] [-c <net_class_ID>] [-a] [-r <K|M|G>]
vznetstat --help
```

### Options

Name	Description
-v <CT_ID>	Displays statistics for a Container with the ID of <CT_ID>.
-c <class>	Shows statistics for the <class> class only.
-a	Displays statistics for all classes.
-r <K M G>	Displays the network statistics, which is shown in bytes by default, in the following measurement units: <ul style="list-style-type: none"> <li>κ: display the network statistics in kilobytes;</li> <li>M: display the network statistics in megabytes;</li> <li>G: display the network statistics in gigabytes.</li> </ul>
--help	Displays utility usage information.

When executed without any options, `vznetstat` displays network statistics, in bytes, for all defined network classes of all running Containers on the Node.

## vzdevctl

Forwards hardware devices existing on the Hardware Node (SCSI, iSCSI, USB flash drives, etc.) to Containers.

### Syntax

```
vzdevctl [--quiet|--verbose] add <CT_ID> --deviceid <name> [--alias <name>]
  [--exclusive] [--connect] [--onboot]
vzdevctl [--quiet|--verbose] remove <CT_ID> --deviceid <name>|--alias <name>
vzdevctl [--quiet|--verbose] connect <CT_ID> --deviceid <name>|--alias <name>
vzdevctl [--quiet|--verbose] dconnect <CT_ID> --deviceid <name>|--alias <name>
vzdevctl [--quiet|--verbose] set <CT_ID> [--deviceid <name>|--alias <name>]
  [--newalias <name>]|--group <name>] [--onboot <yes|no>]
vzdevctl [--quiet|--verbose] devtree [--deviceid <name>|--all|--forwarded]
vzdevctl [--quiet|--verbose] status <CT_ID> [--deviceid <name>|--alias <name>|--all]
vzdevctl [--quiet|--verbose] linkadd <CT_ID> [--symlink <name>] --object <name>
vzdevctl [--quiet|--verbose] linkdel <CT_ID> --symlink <name>|--object <name>
vzdevctl [--quiet|--verbose] linkquery <CT_ID>
```

```
vzdevctl --version
vzdevctl --help
```

## Commands

Name	Description
<b>add</b>	Forwards the hardware device to the specified Container.
<b>remove</b>	Removes the hardware device from the specified Container. If the device is in the active state, it is first disconnected from the Container.
<b>connect</b>	Connects the hardware device to the Container. Before connecting the device to the Container, you must first forward it to this Container.
<b>dconnect</b>	Disconnects the hardware device from the Container.
<b>set</b>	Sets device info. (Forwarded/shared state can be changed after disconnect-connect cycle only)
<b>devtree</b>	Shows all hardware devices available on the Hardware Node.
<b>status</b>	Shows the hardware device status for the specified Container.
<b>linkadd</b>	Adds a symbolic link to the Hardware Node object.
<b>linkdel</b>	Deletes a symbolic link from the specified Container.
<b>linkquery</b>	Displays the symbolic links for the specified Container.

## Options

Name	Description
<b>--deviceid &lt;ID&gt;</b>	<p>The ID to be assigned to the hardware device. It should be set in the following form: <i>Enumerator\Hardware_ID\Instance_ID</i> where:</p> <ul style="list-style-type: none"> <li><i>Enumerator</i> denotes a system component responsible for discovering hardware devices on your Hardware Node (usually, the Plug-an-Play manager).</li> <li><i>Hardware_ID</i> is a vendor-defined identification string used by the Setup program to match a hardware device on your Hardware Node to an INF file.</li> <li><i>Instance_ID</i> is a hardware device identification string that distinguishes the device from other devices of the same type on your Hardware Node.</li> </ul> <p>Detailed information on device identification strings is provided at <a href="http://msdn.microsoft.com/en-US/library/ff541224.aspx">http://msdn.microsoft.com/en-US/library/ff541224.aspx</a>.</p>
<b>--alias &lt;alias&gt;</b>	A short name (alias) to be assigned to the hardware device.
<b>--exclusive</b>	Sets the hardware device forwarding mode to 'exclusive' instead of 'shared' which is set by default. In this case the device cannot be forwarded to any other Container on the Hardware Node. This command must be used for any SCSI or USB-flash device which you are going to forward to a Container.
<b>--connect</b>	Specifies whether the hardware device being forwarded to the Container is also to be connected to the Container.
<b>--onboot &lt;yes no&gt;</b>	Sets whether the hardware device is to be automatically connected to the Container on its startup (yes) or should be manually joined after the Container is up and running (no).
<b>--newalias &lt;name&gt;</b>	Sets new alias for device.

<code>--class</code>	Sets class name filter, may contains a wildcard.
<code>--fname</code>	Sets friendly name filter, may contains a wildcard.
<code>--wizard</code>	Turns on interactive mode which allows to change state of every listed device. For <code>devtree</code> using this mode without any filtering options is strongly unrecommended (too many entries to skip).
<code>--force</code>	Forces the device disconnection for busy devices. This option is strongly unrecommended.
<code>--forwarded</code>	Displays only those hardware devices on the Hardware Node that are currently forwarded to some Containers.
<code>--all</code>	Can be indicated in one of the following cases: <ul style="list-style-type: none"> <li>when used with the <code>devtree</code> command, displays all SCSI devices available on the Hardware Node (connected, not connected, denied);</li> <li>when used with the <code>status</code> command, displays all Container devices including the ones that are currently not connected to the Container.</li> </ul>
<code>--symlink</code>	The full name to be assigned to the symbolic link.
<code>--object</code>	The full name of the object for which you are creating a symlink. If used without the <code>--symlink</code> option, the name specified after this option is also used to denote the Container symbolic link.
<code>--version</code>	Shows the Virtuozzo Containers for Windows version.
<code>--quiet</code>	Disables logging to the log file and screen. Can be used with any commands.
<code>--verbose</code>	Sets the logging level to the maximum value. Can be used with any commands.
<code>--help, /?</code>	Gets the utility usage information and exits.

## vzcpucfg

Manages CPU pools on the Hardware Node. You can do the following:

- create a new CPU pool,
- remove an existing CPU pool,
- list the CPU pools currently existing on the physical server,
- configure the number of CPUs in a CPU pool,
- assign CPU pools to Containers.

### Syntax

```
vzcpucfg pool set <pool_ID> <CPU_range>
vzcpucfg pool del <pool_ID>
vzcpucfg pool list
```

## Options

Name	Description
<b>set</b> <pool_ID> <CPU_range>	Creates a new CPU pool or configures the number of CPUs in an existing CPU pool.
<b>del</b> <pool_ID>	Removes a CPU pools from the physical server.
<b>list</b>	Lists the CPU pools existing on the physical server.
<pool_ID>	The ID to be assigned to the CPU pool or the ID of the CPU pool to be removed from the physical server.
<CPU_range>	The CPU range to be included in the CPU pool. A range may contain one or several CPUs (for example, 1 or 1-3). You can also specify multiple comma-separated ranges at once (e.g., 0-2, 3-6, 8).

## vzquery

Determines the Container ID using either a process ID or a session ID.

### Syntax

```
vzquery s2v <session_ID>
vzquery v2s <CT_ID>
vzquery p2v <process_ID>
```

### Options

Name	Description
<b>s2v</b> <session_ID>	Displays the ID of the Container to which the Terminal Services session with the specified ID is opened.
<b>v2s</b> <CT_ID>	Lists the IDs of all Terminal Services sessions opened to the specified Container.
<b>p2v</b> <process_ID>	Displays the ID of the Container where the process with the specified ID is running.

## vzwinupdatecmd

Lists Windows Server updates installed in Containers.

### Syntax

```
vzwinupdatecmd /listctupd <CT_ID> [...] [/all]
vzwinupdatecmd /help
```

## Options

Name	Description
/listctupd <CT_ID> [ . . . ]	Lists Windows updates currently installed inside the Container(s).
/all	Applies the operation to all Containers on the Hardware Node.
/help, /?	Displays command usage information.

## Custom Action Scripts

The table below lists and describes custom action scripts supported by Virtuozzo Containers for Windows:

Name	Description
vz-precreate.<ext>	Run before a Container is created.
vz-postcreate.<ext>	Run after a Container has been created.
vz-premount.<ext>	Run before Container's private area is mounted.
vz-postmount.<ext>	Run after Container's private area has been mounted.
vz-preunmount.<ext>	Run before Container's private area is unmounted.
vz-postunmount.<ext>	Run after Container's private area is unmounted.
vz-prestart.<ext>	Run before a Container is started.
vz-poststart.<ext>	Run after a Container has been started.
vz-prestop.<ext>	Run before a Container is stopped.
vz-poststop.<ext>	Run after a Container has been stopped.
vz-preclone.<ext>	Run before a Container is copied.
vz-postclone.<ext>	Run after a Container has been copied.
vz-prechangevpsid.<ext>	Run before the Container ID is changed.
vz-postchangevpsid.<ext>	Run after the Container ID has been changed.

## Glossary

**Application template** is a template used to install a set of applications in *Containers*. See also *Template*.

**Container** is a virtual private server, which is functionally identical to an isolated standalone server, with its own IP addresses, processes, files, user database, configuration files, applications, system libraries, and so on. While sharing the same *Hardware Node* and OS kernel, *Containers* are isolated from each other. A *Container* is a kind of 'sandbox' for processes and users.

**Hardware Node** (or **Node**) is the server where *Virtuozzo Containers for Windows* is installed.

**Host Operating System** (or **Host OS**) is an operating system installed on the *Hardware Node*.

**OS template** (or **Operating System template**) is used to create new *Containers* with a preinstalled operating system. See also *Template*.

**Virtuozzo Containers for Windows** is a complete server automation and virtualization solution that allows you to create multiple isolated *Containers* on a single physical server to share hardware, licenses, and management effort with maximum efficiency.

**Virtuozzo Containers for Windows license** is a special license which you must install on a *Hardware Node* to be able to use *Virtuozzo Containers for Windows*. Every *Hardware Node* must have a license installed.

**Virtuozzo File System (VZFS)** is a virtual file system for mounting to *Container* private areas. VZFS symlinks are seen as real files inside *Containers*.

**Virtuozzo Power Panel** is a tools for managing personal *Containers* via a standard Web browser.

**Virtuozzo Automator** is a tool for managing *Hardware Nodes* and *Containers* residing on them via a standard Web browser.

**Private area** is a location where *Container* files which are not shared with other *Containers* are stored.

**Template** is a set of original application files (packages) repackaged for using inside *Containers*. There are two types of templates: *OS Templates* are used to create new *Containers* with a preinstalled operating system, *application templates* are used to install applications or sets of applications in *Containers*.

# Index

## A

About This Guide - 6  
About Virtuozzo Containers for Windows 6.0  
- 5

## B

Backup and Restoration Tools - 35

## C

Custom Action Scripts - 53

## G

General-Purpose Tools - 11  
Getting Help - 7  
Glossary - 54

## I

Introduction - 5

## L

Licensing Tools - 29

## M

Migration Tools - 31

## O

Organization of This Guide - 7

## S

Supplementary Tools - 43

## T

Template Management Tools - 40

## V

Virtuozzo Containers for Windows Utilities  
Overview - 9  
vzabackup - 35  
vzarestore - 37  
vzcache - 44

vzcpucfg - 51  
vzctl - 11  
vzctl addrole, vzctl delrole, vzctl enumrole -  
23  
vzctl create - 12  
vzctl defrag - 22  
vzctl delete, vzctl destroy - 13  
vzctl exec, vzctl exec2, and vzctl enter - 20  
vzctl mount, vzctl umount - 14  
vzctl mounttext, vzctl umounttext - 20  
vzctl partadd, vzctl partdel - 21  
vzctl reinstall - 21  
vzctl set - 14  
vzctl shrink - 22  
vzctl start, vzctl stop, vzctl restart, and vzctl  
status - 14  
vzdevctl - 49  
vzkeygen - 43  
vzlicload - 29  
vzlicview - 30  
vzlist - 23  
vzlist Output Parameters and Their Modifiers -  
24  
vzlscache - 46  
vzmigrate - 31  
vzmlocal - 33  
vznetcfg - 47  
vznetstat - 49  
vzp2v - 32  
vzpkgadd - 41  
vzpkgdeploy - 41  
vzpkgls - 40  
vzpkgrm - 42  
vzquery - 52  
vzquota - 26  
vzquota setlimit - 27  
vzquota stat, vzquota show - 28  
vzuncache - 46  
vzvssctl - 39  
vzwinupdatecmd - 52